# **EV3 Color Sensor**

#### Non-Visible component

Category	Requires	Version
LEGO® MINDSTORMS® > EV3	API 19, Android 4.4 - 4.4.4 KitKat	0

# Overview

A component that provides a high-level interface to a color sensor on a LEGO MINDSTORMS EV3 robot.

# **Events**

## Above Range


Light level has gone above the range.

# Below Range

Light level has gone below the range.

# Color Changed

Called when the detected color has changed. The ColorChanged event will occur if the Mode property is set to "color" and the ColorChangedEventEnabled property is set to True.



# Within Range

Light level has gone within the range.

# Methods

### Get Color Code

### Returns: Number

It returns the color code from 0 to 7 corresponding to no color, black, blue, green, yellow, red, white and brown.

### Get Color Name

## Returns: Text

Return the color name in one of "No Color", "Black", "Blue", "Green", "Yellow", "Red", "White", "Brown".

# Get Light Level

### Returns: Number

It returns the light level in percentage, or -1 when the light level cannot be read.

## Set Ambient Mode

Make the sensor read the light level without reflected light.

#### Set Color Mode

Enter the color detection mode.

## Set Reflected Mode

Make the sensor read the light level with reflected light.

# **Properties**

## Above Range Event Enabled

```
Boolean Default: False — Read Write - Designer Blocks
```

Whether the AboveRange event should fire when the light level goes above the TopOfRange.

## Below Range Event Enabled

```
Boolean Default: False — Read Write - Designer Blocks
```

Whether the BelowRange event should fire when the light level goes below the BottomOfRange.

### Bluetooth Client

```
Component — Read Write - Designer Blocks
```

The BluetoothClient component that should be used for communication.

# Bottom Of Range

```
Number Default: 30 — Read Write - Designer Blocks
```

The bottom of the range used for the BelowRange, WithinRange, and AboveRange events.

# Color Changed Event Enabled

Whether the ColorChanged event should fire when the Mode property is set to "color" and the detected color changes.

### Mode

```
Text Default: reflected — Read Write - Designer Blocks
```

Specifies the mode of the sensor.

#### Sensor Port

```
Text Default: 1 — Write - Designer
```

The sensor port that the sensor is connected to.

## Top Of Range

```
Number Default: 60 — Read Write - Designer Blocks
```

The top of the range used for the BelowRange, WithinRange, and AboveRange events.

## Within Range Event Enabled

```
Boolean Default: False — Read Write - Designer Blocks
```

Whether the WithinRange event should fire when the light level goes between the BottomOfRange and the TopOfRange.

Last update: January 26, 2020